

PROGRAM LISTING

MOVE DIGIT

BLCK 0210A

.CGEC12,019,026L3LLC653681001,008012,00110011E361080A21/340080 1 OF 2 0210A 02
 .037044N000,340244,348349,357,361368/333080 PROG. CHAIN. ROUTINE 2 OF 2 0210A 03
 LG57S4510012,045LL772772/2772#140/60#780L/892702/2702413 CARD 1 OF 3 0210A 04
 .019026,033,040C44,051051/340001 TITLE PRINT ROUTINE CARD 2 OF 3 0210A 05
 .SG1SC5,512,513S17,518S25,529S36,537S41,545/333080 CARD 3 OF 3 0210A 06

LOAD	INST	ADDR	ADDR	OP	A	B	REMARKS	
396	377	B	389				USE WHEN TESTS ARE RUN FROM TAPE	07
404	385	B	58E				**	08
408	389	N	C0C				**	09
412	393	M	36C	392			**	10
419	400	/	332				START TEST	11
423	404	/						12
424	405	B	50C	5521			BR TO TITLE PRINT ROUTINE IF 1 IN 552	13
432	413	/	08C				CLEAR REAC AREA	14
436	417	B	348				BRANCH TO PROGRAM CHAINING ROUTINE	15
440	421	.	C01	C78			LOAD PRINT AREA	16
447	428	L	08C	299			**	17
454	435	L	C72	272			**	18
461	442	.	221	241			**	19
468	449	L	225	265			**	20
475	456	D	205	265			MOVE DIGIT CP WITH CHAINING	21
482	463	C					**	22
483	464	D					**	23
484	465	C					**	24
485	466	D					**	25
486	467	B	45C	E			B ON TO SCOPE	26
491	472	C	265	245			TEST FOR ERRCR	27
498	479	B	90C	/			BRANCH TO ERROR PRINT ROUTINE IF UNEQ	28
503	484	E	95C	C			C ON TO CORRECT PRINT ROUTINE	29
508	489	B	95E				BRANCH TO SENSE D	30
919	900	L	/14	285			BEGIN ERRCR PRINT ROUTINE	31
926	907	B	91C	E			E ON TO ERRCR STOP	32
931	912	2	95E				ERRCR PRINT	33
935	916	.	95E				ERRCR STOP	34
939	920						WORD MARK	35
969	950	L	/19	285			CORRECT PRINT ROUTINE	36
976	957	2					**	37
977	958	E	421	C			D ON TO REPEAT	38
982	963	E	417				BRANCH TO REAC NEXT RECORD	39
/29	/10	E	RRC	R			CONSTANTS	40
/34	/15						**	41
/39	/20	A	F1	ELD			**	42
/59	/40	B	F1	ELD			**	43
/79	/60	R	ESL	LT SHOULD BE			**	44
/99	/80	R	ESL	LT IS			**	45
.019027,031,038042BC31T90#400L046352BW04BS88							MOVE DIGIT	0210A 46

0210A-4

DATE							
ENG. CHG. NO.							