

PROGRAM LISTING

619	600	A	971	47C	''	48
626	607	L	47C	467	MAKE A FIELD 2 GREATER THAN B FIELD	49
633	614	A	971	467	''	50
640	621	□	465	46E	''	51
647	628	B	464		BRANCH TO COMPARE NEXT SET OF CHARACTERS	52
651	632	B	512	B	B ON TO SCOPE	53
656	637	B	#1C		BRANCH TO ERROR PRINT ROUTINE	54
669	650	,	7C1		CONSTANTS TO SET INSTR TO INITIAL COND	55
673	654	C	7C4	702	''	56
680	661	B	2E		CONSTANTS TO DETECT END OF TABLE	57
683	664	B	3C		''	58
686	667	F	IGH		CONSTANTS FOR PRINTCUTS	59
691	672	L	CW		''	60
696	677	E	QUA	L	''	61
701	682	E	RRC	R	''	62
720	701	.	□	£ \$ *	TABLE USED IN COMPARING	63
740	721	-	/	, %	''	64
760	741	#	2	£ A B C D	''	65
780	761	E	F	G H I - J K L M	''	66
800	781	N	C	P Q R + S T L V	''	67
820	801	W	X	Y Z 0 1 2 3 4 5	''	68
840	821	6	7	819 91	''	69
869	850	Y	85C	733	GENERATE WORD SEPARATOR CHARAC FOR TABLE	70
876	857	Y	857	739	GENERATE A BIT FOR TABLE	71
883	864	B	434		BRANCH TO SET WORD MARKS IN TABLE	72
919	900	,	929	936	ERROR PRINT ROUTINE IF NO BR OCCURRED	73
926	907	M	467	931	ON LOW CONDITION	74
933	914	M	47C	93E	''	75
940	921	□	929	936	''	76
947	928	L	AAA	202	''	77
954	935	L	BBB	222	''	78
961	942	L	676	245	''	79
968	949	B	985	U	''	80
973	954	B	996	S	''	81
978	959	L	686	285	''	82
985	966	B	975	E	E ON TO ERROR STOP	83
990	971	2	976		ERROR PRINT	84
994	975	.			ERROR STOP	85
995	976	B	464	D	D ON TO REPEAT SAME COMPARE	86
#00	981	B	49C		BRANCH TO CONTINUE TEST	87
#04	985	L	671	265	LOAD -RESULT IS- COMMENT	88
#11	992	B	959		''	89
#15	996	L	681	265	''	90
#22	#03	B	959		''	91
#29	#10	,	#39	#46	ERROR PRINT ROUTINE IF BRANCH OCCURRED	92
#36	#17	M	515	#41	ON HIGH CONDITION	93
#43	#24	M	518	#48	''	94
#50	#31	□	#39	#46	''	95
#57	#38	L	AAA	202	''	96
#64	#45	L	BBB	222	''	97
#71	#52	L	671	245	''	98

3310A-7

DATE							
ENG. CHG. NO.							