

PG LIN	CT	LABEL	OP	A OPERAND	B OPERAND	D	LOC	INSTRUCTION COMMENTS	C8002
15 130	8		MCW	%TO	C97010- 26	W	1144	M %TO S26 W	WR ENTER INFO
15 131	8		MCW	%TO	0161	W	1152	M %TO 161 W	WR SPACE
15 140	4		H	P15120		W	1160	- /39	HALT & BR BACK
15 150	8	P15150	MCW	%TO	C97100- 26	W	1164	M %TO S82 W	WRITE INFO LINE
15 160	8		LCA	%TO	0618	R	1172	L %TO 618 R	READ LINE TO CK
15 161	8		LCA	%TO	0618	W	1180	L %TO 618 W	WR CK LINE--EYE
15 162	8		MCW	%TO	0161	W	1188	M %TO 161 W	WR SPACE
15 170	5		B	P15190		%	1196	B S05 %	BR ERROR
15 180	4		B	P15220		W	1201	B S17	BR NO ERROR
15 190	8	P15190	MCW	%TO	0503	W	1205	M %TO 503 W	WRITE ERR INST
15 200	4		H	P15120		W	1213	- /39	HALT & BR BACK
15 220	5	P15220	B	P10010		D	1217	B 708 D	BR CONT LOOP
15 230	4		B	0348		D	1222	B 348	
90 000				* CONSTANTS					
90 010	11	C90010	DCW	0628	0123456789		0628		
90 020	9		DCW	0637	ABCDEFGHI		0637		
90 030	9		DCW	0646	JKLMNOPQR		0646		
90 040	11		DCW	0657	/STUVWXYZ :		0657		
90 050	9	C90050	DCW	0666	@/>+"#=Δ		0666		
90 060	8		DCW	0674	;-(<@!*		0674		
90 070	8		DCW	0682	*)0#;!;*		0682		
90 080	15	C90080	DCW	0697	LINE 1.		0697		
90 090	1		DCW	0698	./		0698		
90 100	1		DCW	0699			0699		
91 010	10	C91010	DCW	0090	.@(<@&\$*);		0090		
91 020	10	C91020	DCW	0100	Δ-/,%Z="=#		0100		
91 030	10		DCW	0110	@:>/ ?ABC		0110		
91 040	10		DCW	0120	DEFGHI:JKL		0120		
91 050	10		DCW	0130	MNOPQR#STU		0130		
91 060	10		DCW	0140	VWXYZ 012		0140		
91 070	10		DCW	0150	3456789		0150		
91 080	10		DCW	0160	LINE 2.		0160		
91 090	1		DCW	0161			0161		
92 010	10	C92010	DCW	0545	1QAZ2WSX3E		0545		
92 020	10		DCW	0555	DC4RFV5TGB		0555		
92 030	10		DCW	0565	6YHN7UJMBI		0565		
92 040	10		DCW	0575	K,90L-OP?/		0575		
92 050	10		DCW	0585	!;# "i@(<		0585		
92 060	10		DCW	0595	:;@</*>=)		0595		