

```
CLEAR STORAGE 1 ,008015,022026,030037,044,049,053053N000000N00001026 1
CLEAR STORAGE 2 L068116,105106,110117B101/I9I#071029C029056B026/B001/0991,001/001117I0? 2
BOOTSTRAP ,008015,022029,036040,047054,061068,072/061039 ,0010011040 3
```

FORTRAN COMPILER -- ARITH PHASE THREE -- PHASE 35 PAGE 1

SEQ	PG	LIN	LABEL	OP	OPERANDS	SFX	CT	LOCN	INSTRUCTION	TYPE	CARD
101				JOB	FORTRAN COMPILER -- ARITH PHASE THREE -- PHASE 35						
102				CTL	6611						
103				*							
104				*	INITIALIZATION FOR ARITH PHASE FOUR TAKES PLACE.						
105				*							
106				*	STUFF IN THE RESIDENT AREA						
107				*							
108				PHASID EQU	110 PHASE ID, FOR SNAPSHOT DUMPS			0110			
109				SNAPSH EQU	333 CORE DUMP SNAPSHOT			0333			
110				LOADNX EQU	700 LOAD NEXT OVERLAY			0700			
111				CLEARL EQU	707 CS AT START OF OVERLAY LOADER			0707			
112				*							
113				ORG	838				0838		
114				LOADDD EQU	*&1 LOAD ADDRESS			0838			
115	838		BEGINN	BSS	SNAPSH,C	5	0838		B 333 C		4
116	843		SBR	CLEARL&3,GMWM		7	0843		H 710 68		4
117	850		LCA	ARITH4,PHASID		7	0850		L 67 110		4
118	857		B	LOADNX		4	0857		B 700		4
119	910		DC	#50		50	0910				6
120	960		DC	#50		50	0960				8
121	1 010		DC	#50		50	1010				10
122	1 060		DC	#50		50	1060				12
123	1 067	ARITH4	DCW	@ARITH 4@		7	1067				12
124	1 068	GMWM	DCW	@j@		1	1068			GMARK	12
125			ORG	201					0201		
126	203		DSA	LOADDD	LOAD ADDRESS FOR CARD-TO-TAPE PROGRAM	3	0203		838		13
127			EX	BEGINN					B 838		14
128			END						/ 000 080		

