

PROGRAM LISTING

EDIT

BLOCK 03708

.008012,019,026030L0653681001,008012,001100118361080AB421/340080 1 JF 2 03708 02
 ,037044N000,340344,348349,357,361369/333080 PROG. CHAIN. ROUTINE 2 OF 2 03708 03
 L05754510C12,049L0772772/27720/60/600/80L/892702/2702413 CARD 1 OF 3 03708 04
 ,019026,033,040044,051051/340001 TITLE PRINT ROUTINE CARD 2 OF 3 03708 05
 ,S01S05,S12,S13S17,S18S25,S29S36,S37S41,S45/333080 CARD 3 OF 3 03708 06

LOAD INST

ADDR ADDR JP A B

REMARKS

396	377	D	389		USE WHEN TESTS ARE RUN FROM TAPE	07
404	385	B	584		..	08
408	389	N	000		..	09
412	393	M	360	392	..	10
419	400	/	532		START TEST	11
423	404	/				12
424	405	H	500	5521	BR TO TITLE PRINT ROUTINE IF 1 IN S52	13
432	413	/	080		CLEAR READ AREA	14
436	417	H	348		BRANCH TO PROGRAM CHAINING ROUTINE	15
440	421	.	001	078	LOAD PRINT AREA	16
447	428	L	080	299	..	17
454	435	L	072	272	..	18
461	442	.	221	241	..	19
468	449	L	237	277	LOAD CONTROL WORD	20
475	456	E	208	277	EDIT	21
482	463	B	449	B	B ON TO SCOPE	22
487	468	C	277	257	TEST FOR ERROR	23
494	475	B	900	/	BRANCH TO ERROR PRINT ROUTINE IF UNEQ	24
499	480	B	950	C	C ON TO CORRECT PRINT ROUTINE	25
504	485	B	958		BRANCH TO SENSE D	26
919	900	L	114	285	BEGIN ERROR PRINT ROUTINE	27
926	907	B	916	E	E ON TO ERROR STOP	28
931	912	2	958		ERROR PRINT	29
935	916	.	958		ERROR STOP	30
939	920				WORD MARK	31
969	950	L	119	285	CORRECT PRINT ROUTINE	32
976	957	2			..	33
977	958	B	421	D	D ON TO REPEAT	34
982	963	B	417		BRANCH TO READ NEXT RECORD	35
129	110	E	RR0	R	CONSTANTS	36
134	115				..	37
139	120	A	FI	ELD	..	38
159	140	B	FI	ELU	..	39
179	160	R	ESL	LT SHOULD BE	..	40
199	180	R	ESL	LT IS	..	41
019027,031,038042H031T98#B400L0463528W048588					EDIT	03708 42
					DETAIL CARDS	
00000012			EEEEEE	00000012		03708 43
00000034		0	EEEEEE	000034		03708 44
00000056		0	EEEEEE	0056		03708 45

03708-4

DATE							
ENO. CHG. NO							